



Thu Aug 29 14:44:43 PDT 2019

FreeBSD/amd64 (freenas.local) (ttyv0)

Console setup

- ▶ Configure Network Interfaces
 - Configure Link Aggregation
 - Configure VLAN Interface
- 4) Configure Default Route
- 5) Configure Static Routes
- 6) Configure DNS
- 7) Reset Root Password
- 8) Reset Configuration to Defaults
- 9) Shell
- 10) Reboot
- 11) Shut Down

The web user interface is at:

<http://0.0.0.0>

Enter an option from 1-11:



```
7) Reset Root Password
8) Reset Configuration to Defaults
9) Shell
10) Reboot
11) Shut Down
```

The web user interface is at:

```
http://0.0.0.0
```

Enter an option from 1-11: 1

```
1) vtnet0
```

Select an interface (q to quit): 1

Remove the current settings of this interface? (This causes a momentary disconnection of the network.) (y/n) n

Configure interface for DHCP? (y/n) n

Configure IPv4? (y/n) y

Interface name:foo

Several input formats are supported

Example 1 CIDR Notation:

```
192.168.1.1/24
```

Example 2 IP and Netmask separate:

```
IP: 192.168.1.1
```

```
Netmask: 255.255.255.0, /24 or 24
```

```
IPv4 Address:144.38.193.200
```



```
Configure IPv6? (y/n) n
Aug 29 14:51:57 freenas dhclient[1857]: connection closed
Aug 29 14:51:57 freenas dhclient[1857]: exiting.
Restarting network: ok
```

Console setup

- ▶ Configure Network Interfaces
 - ▶ Configure Link Aggregation
 - ▶ Configure VLAN Interface
- 4) Configure Default Route
- 5) Configure Static Routes
- 6) Configure DNS
- 7) Reset Root Password
- 8) Reset Configuration to Defaults
- 9) Shell
- 10) Reboot
- 11) Shut Down

The web user interface is at:

<http://144.38.193.200>

Enter an option from 1-11: 4



```
IPv4 Default Route:144.38.193.193
Saving IPv4 gateway: Ok
Configure IPv6 Default Route? (y/n)n
Restarting routing: ok
```

Console setup

- ▶ Configure Network Interfaces
 - Configure Link Aggregation
 - Configure VLAN Interface
- 4) Configure Default Route
- 5) Configure Static Routes
- 6) Configure DNS
- 7) Reset Root Password
- 8) Reset Configuration to Defaults
- 9) Shell
- 10) Reboot
- 11) Shut Down

The web user interface is at:

<http://144.38.193.200>

Enter an option from 1-11: 6

Console setup

- 1) Configure Network Interfaces
- 2) Configure Link Aggregation
- 3) Configure VLAN Interface
- 4) Configure Default Route
- 5) Configure Static Routes
- 6) Configure DNS
- 7) Reset Root Password
- 8) Reset Configuration to Defaults
- 9) Shell
- 10) Reboot
- 11) Shut Down

The web user interface is at:

<http://144.38.193.200>

Enter an option from 1-11: 6

DNS Domain [local]:

Enter nameserver IPs, an empty value ends input

DNS Nameserver 1:144.38.192.2

DNS Nameserver 2:144.38.192.3

DNS Nameserver 3:8.8.8.8